

Open Object Rexx™

RxSock TCP/IP Socket Functions Reference

Version 3.2.0 Edition

Revision 0

October 25, 2007



**W. David Ashley
Rony G. Flatscher
Mark Hessling
Rick McGuire
Mark Miesfeld
Lee Peedin**

Open Object Rexx™: RxSock TCP/IP Socket Functions Reference

by

W. David Ashley

Rony G. Flatscher

Mark Hessling

Rick McGuire

Mark Miesfeld

Lee Peedin

Version 3.2.0 Edition

Published October 25, 2007

Copyright © 1995, 2004 IBM Corporation and others. All rights reserved.

Copyright © 2005, 2006, 2007 Rexx Language Association. All rights reserved.

This program and the accompanying materials are made available under the terms of the [Common Public License Version 1.0](#).

Before using this information and the product it supports, be sure to read the general information under [Notices](#).

This document was originally owned and copyrighted by IBM Corporation 1995, 2004. It was donated as open source under the [Common Public License Version 1.0](#) to the Rexx Language Association in 2004.

Thanks to Julian Choy for the ooRexx logo design.

Table of Contents

About This Book	v
1. Related Information	v
2. How to Read the Syntax Diagrams	v
3. A Note About Program Examples in this Document	vi
4. Getting Help	vi
4.1. The Rexx Language Association Mailing List	vi
4.2. The Open Object Rexx SourceForge Site	vii
4.3. comp.lang.rexx Newsgroup	viii
1. What is RxSock?	1
2. Installation and Removal	3
3. Parameters and Return Values	5
3.1. Stem Variables	6
4. Special Variables	9
5. Function Reference	11
5.1. SockLoadFuncs	11
5.2. SockDropFuncs	12
5.3. SockVersion	12
5.4. SockAccept	12
5.5. SockBind	14
5.6. SockClose	15
5.7. SockConnect	16
5.8. SockGetHostByAddr	18
5.9. SockGetHostByName	18
5.10. SockGetHostId	19
5.11. SockGetPeerName	19
5.12. SockGetSockName	20
5.13. SockGetSockOpt	21
5.14. SockInit	24
5.15. SockIoctl	24
5.16. SockListen	25
5.17. SockPSock_Erno	26
5.18. SockRecv	26
5.19. SockRecvFrom	28
5.20. SockSelect	29
5.21. SockSend	31
5.22. SockSendTo	32
5.23. SockSetSockOpt	34
5.24. SockShutDown	36
5.25. SockSock_Erno	37
5.26. SockSocket	38
5.27. SockSoClose	39
A. Notices	41
A.1. Trademarks	41
A.2. Source Code For This Document	42

B. Common Public License Version 1.0	43
B.1. Definitions	43
B.2. Grant of Rights	43
B.3. Requirements	44
B.4. Commercial Distribution	44
B.5. No Warranty	45
B.6. Disclaimer of Liability	45
B.7. General	46
Index	47

About This Book

This book describes the Open Object Rexx™ TCP/IP Sockets Function Library. .

This book is intended for people who plan to develop applications using Rexx and TCP/IP sockets. Its users range from the novice, who might have experience in some programming language but no Rexx or sockets experience, to the experienced application developer, who might have had some experience with Object Rexx and sockets.

This book is a reference rather than a tutorial. It assumes you are already familiar with object-oriented programming concepts.

Descriptions include the use and syntax of the language and explain how the language processor "interprets" the language as a program is running.

1. Related Information

See also: *Open Object Rexx: Reference*

2. How to Read the Syntax Diagrams

Throughout this book, syntax is described using the structure defined below.

- Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

The >>--- symbol indicates the beginning of a statement.

The ---> symbol indicates that the statement syntax is continued on the next line.

The >--- symbol indicates that a statement is continued from the previous line.

The --->< symbol indicates the end of a statement.

Diagrams of syntactical units other than complete statements start with the >--- symbol and end with the ---> symbol.

- Required items appear on the horizontal line (the main path).

```
>>-STATEMENT--required_item-----><
```

- Optional items appear below the main path.

```
>>-STATEMENT--+-----+-----><
               +-optional_item-+
```

- If you can choose from two or more items, they appear vertically, in a stack. If you must choose one of the items, one item of the stack appears on the main path.

```
>>-STATEMENT--+required_choice1+-----><
               +-required_choice2-+
```

- If choosing one of the items is optional, the entire stack appears below the main path.

```
>>-STATEMENT--+-----+-----><
               +-optional_choice1-+
```

```
+--optional_choice2--+
```

- If one of the items is the default, it appears above the main path and the remaining choices are shown below.

```
+--default_choice--+
>>-STATEMENT--+-+-----+-----><
+--optional_choice--+
+--optional_choice--+
```

- An arrow returning to the left above the main line indicates an item that can be repeated.

```
+-----+
V      |
>>-STATEMENT----repeatable_item+-----><
```

A repeat arrow above a stack indicates that you can repeat the items in the stack.

- A set of vertical bars around an item indicates that the item is a fragment, a part of the syntax diagram that appears in greater detail below the main diagram.

```
>>-STATEMENT--| fragment |-----><
```

fragment:

```
|--expansion_provides_greater_detail-----|
```

- Keywords appear in uppercase (for example, PARM1). They must be spelled exactly as shown but you can type them in upper, lower, or mixed case. Variables appear in all lowercase letters (for example, parm_x). They represent user-supplied names or values.
- If punctuation marks, parentheses, arithmetic operators, or such symbols are shown, you must enter them as part of the syntax.

The following example shows how the syntax is described:

```
+-,-----+
V      |
>>-MAX(---number+---)-----><
```

3. A Note About Program Examples in this Document

The program examples in this document are rendered in a mono-spaced font that is not completely compatible for cut-and-paste functionality. Pasting text into an editor could result in some characters outside of the standard ASCII character set. Specifically, single-quote and double-quote characters are sometimes converted incorrectly when pasted into an editor.

4. Getting Help

The Open Object Rexx Project has a number of methods to obtain help for ooRexx. These methods, in no particular order of preference, are listed below.

4.1. The Rexx Language Association Mailing List

The *Rexx Language Association* (<http://www.rexxla.org/>) maintains a mailing list for its members. This mailing list is only available to RexxLA members thus you will need to join RexxLA in order to get on the list. The dues for RexxLA membership are small and are charged on a yearly basis. For details on joining RexxLA please refer to the *RexxLA Home Page* (<http://rexxla.org/>) or the *RexxLA Membership Application* (http://rexxla.org/About_RexxLA/member.html) page.

4.2. The Open Object Rexx SourceForge Site

The Open Object Rexx Project (<http://www.oorexx.org/>) utilizes *SourceForge* (<http://sourceforge.net/>) to house the *ooRexx Project* (<http://sourceforge.net/projects/oorexx>) source repositories, mailing lists and other project features. Here is a list of some of the most useful facilities.

The ooRexx Forums

The ooRexx project maintains a set of forums that anyone may contribute to or monitor. They are located on the *ooRexx Forums* (http://sourceforge.net/forum/?group_id=119701) page. There are currently three forums available: Help, Developers and Open Discussion. In addition, you can monitor the forums via email.

The Developer Mailing List

You can subscribe to the oorexx-devel mailing list at *ooRexx Mailing List Subscriptions* (http://sourceforge.net/mail/?group_id=119701) page. This list is for discussing ooRexx project development activities. It also supports a historical archive of past messages.

The Users Mailing List

You can subscribe to the oorexx-users mailing list at *ooRexx Mailing List Subscriptions* (http://sourceforge.net/mail/?group_id=119701) page. This list is for discussing using ooRexx. It also supports a historical archive of past messages.

The Announcements Mailing List

You can subscribe to the oorexx-announce mailing list at *ooRexx Mailing List Subscriptions* (http://sourceforge.net/mail/?group_id=119701) page. This list is only used to announce significant ooRexx project events.

The Bug Mailing List

You can subscribe to the oorexx-bugs mailing list at *ooRexx Mailing List Subscriptions* (http://sourceforge.net/mail/?group_id=119701) page. This list is only used for monitoring changes to the ooRexx bug tracking system.

Support Requests

You can create a support request at *ooRexx Support Request* (http://sourceforge.net/tracker/?group_id=119701&atid=684731) page. Please be sure to log in to Sourceforge before creating the request so that it will record your e-mail address. This will allow SourceForge (and the ooRexx developers) a way to contact you when updates are made to your

request. Otherwise you will need to manually check back on this page to track any updates to the request.

Also, please try to provide as much information in the support request as possible so that the developers can determine the problem as quickly as possible.

Bug Reports

You can create a bug report at *ooRexx Bug Report* (http://sourceforge.net/tracker/?group_id=119701&atid=684730) page. Please be sure to log in to Sourceforge before creating the report so that it will record your e-mail address. This will allow SourceForge (and the ooRexx developers) a way to contact you when updates are made to your report. Otherwise you will need to manually check back on this page to track any updates to the report.

Also, please try to provide as much information in the bug report as possible so that the developers can determine the problem as quickly as possible.

Patch Reports

If you create an enhancement patch for ooRexx please post the patch using the *ooRexx Patch Report* (http://sourceforge.net/tracker/?group_id=119701&atid=684732) page. Please be sure to log in to Sourceforge before creating the report so that it will record your e-mail address. This will allow SourceForge (and the ooRexx developers) a way to contact you when updates are made to your report. Otherwise you will need to manually check back on this page to track any updates to the report.

Also, please try to provide as much information in the patch report as possible so that the developers can evaluate the enhancement as quickly as possible.

Please do not post bug patches here, instead you should open a bug report and attach the patch to it.

4.3. comp.lang.rexx Newsgroup

The comp.lang.rexx (news:comp.lang.rexx) newsgroup is a good place to obtain help from many individuals within the Rexx community. You can obtain help on Open Object Rexx or on any number of other Rexx interpreters and tools.

Chapter 1. What is RxSock?

RxSock is a Rexx function package providing access to the TCP/IP socket APIs available to the C programming environment. Most of the functions described in this reference are similar to the corresponding C functions available in the TCP/IP socket library.

It is assumed that you are familiar with the basic socket APIs and can reference those specific to the system. For more information, refer to the book *Internetworking with TCP/IP, Volume I: Principles, Protocols and Architecture* by Douglas Comer (Prentice Hall PTR).

The RxSock package requires TCP/IP support to be active on your system.

Chapter 2. Installation and Removal

The RxSock package is contained in the file rxsock.dll. This file must be placed in a directory listed in your LIBPATH. To get access to the functions in the RxSock package, execute the following Rexx code:

```
If RxFuncQuery("SockDropFuncs") then
do
  rc = RxFuncAdd("SockLoadFuncs", "rxsock", "SockLoadFuncs")
  rc = SockLoadFuncs()
end
```

To unload the DLL, call the SockDropFuncs() function and then exit all CMD.EXE shells. After exiting all command shells, the DLL is dropped by the system and can be deleted or replaced.

Chapter 3. Parameters and Return Values

Unless otherwise stated, the return values are the same as for the corresponding C functions. The following standard parameter types are referred to throughout this reference:

`socket`

is a socket value, which is an integral number.

`domain`

is a domain value. Currently, only the domain `AF_INET` is supported.

`address`

is the stem of a stem variable with the following values:

`address.family`

must always be `AF_INET`.

`address.port`

is a port number.

`address.addr`

is a dotted decimal address or `INADDR_ANY`, where appropriate.

When this parameter is needed, set it the name of a stem variable for the function to set (or that the function will read from). For example, if you pass the string `xxx.!` as a parameter, the following variables are set or queried by the function:

```
"xxx.!family"  
"xxx.!port"  
"xxx.!addr"
```

A null address is an address with the family field being `AF_INET`, the port field being 0, and the `addr` field being 0.0.0.0.

`dotAddress`

is the standard dotted decimal address. For example, the string 9.23.19.63 is a valid address.

`host`

is the stem of a stem variable with the following values:

`host.name`

is the standard name of the host.

`host.alias.0`

is the number of aliases for this host.

host.alias.1

is the first alias for this host.

host.alias.n

is the nth alias for this host.

host.addrtype

must always be AF_INET.

host.addr

is a dotted decimal address (default address).

host.addr.0

is the number of addresses for this host.

host.addr.1

is the first address for this host.

host.addr.n

is the nth address for this host.

When this parameter is needed, set it the name of a stem variable for the function to set (or that the function will read from). For example, if you pass the string xxx.! as a parameter, the following variables are set or queried by the function:

```
"xxx.!name"  
"xxx.!alias.0", "xxx.!alias.1" ... "xxx.!alias.n"  
"xxx.!addrtype"  
"xxx.!addr"  
"xxx.!addr.0", "xxx.!addr.1" ... "xxx.!addr.n"
```

3.1. Stem Variables

The address and host type of a parameter are stems of a stem variable. Normally, when you pass a string like addr. as a parameter, you expect the variables addr.family, addr.port, and addr.addr to be set by the function. In the previous examples, however, the stem contained an exclamation mark. This exclamation mark helps prevent the value that follows from getting misused as a normal variable. Example:

```
port = 923  
sNew = SockAccept(sOld, "addr.")  
say addr.port
```

In this example, you might expect the say statement to write the port number of the accepted socket. Instead, it writes the value of the variable, namely addr.923, because the port variable is set to this value.

Because exclamation marks are rarely used in variables, it is unlikely that the variable !port is used in your program.

Note: Do not use the characters `_`, `0`, and `1` to prefix tail values. `0` and `1` are difficult to distinguish from `O`, `I`, and `I`.

Chapter 4. Special Variables

The following variables are maintained by the system: `errno` and `h_errno`.

Variable *errno*

The variable `errno` is set after each RxSock call. It can have one of the following values or any other numeric value:

- `EWOULDBLOCK`
- `EINPROGRESS`
- `EALREADY`
- `ENOTSOCK`
- `EDESTADDRREQ`
- `EMSGSIZE`
- `EPROTOTYPE`
- `ENOPROTOOPT`
- `EPROTONOSUPPORT`
- `ESOCKTNOSUPPORT`
- `EOPNOTSUPP`
- `EPFNOSUPPORT`
- `EAFNOSUPPORT`
- `EADDRINUSE`
- `EADDRNOTAVAIL`
- `ENETDOWN`
- `ENETUNREACH`
- `ENETRESET`
- `ECONNABORTED`
- `ECONNRESET`
- `ENOBUFS`
- `EISCONN`
- `ENOTCONN`
- `ESHUTDOWN`
- `ETOOMANYREFS`
- `ETIMEDOUT`
- `ECONNREFUSED`
- `ELOOP`

- ENAMETOOLONG
- EHOSTDOWN
- EHOSTUNREACH
- ENOTEMPTY

Note: The value is set even if the function called does not set the variable, in which case the value has no meaning. A value of 0 indicates that no error occurred.

Variable *h_errno*

The variable *h_errno* is set after each RxSock call. It can have one of the following values or any other numeric value:

- HOST_NOT_FOUND
- TRY_AGAIN
- NO_RECOVERY
- NO_ADDRESS

Note: The value is set even if the function called does not set the variable, in which case the value has no meaning. A value of 0 indicates that no error occurred.

Chapter 5. Function Reference

The following sections describe how the individual functions contained in RxSock are invoked from the Rexx programming environment:

- [SockLoadFuncs](#)
- [SockDropFuncs](#)
- [SockVersion](#)
- [SockAccept](#)
- [SockBind](#)
- [SockClose](#)
- [SockConnect](#)
- [SockGetHostByAddr](#)
- [SockGetHostByName](#)
- [SockGetHostId](#)
- [SockGetPeerName](#)
- [SockGetSockName](#)
- [SockGetSockOpt](#)
- [SockInit](#)
- [SockIoctl](#)
- [SockListen](#)
- [SockPSock_Erno](#)
- [SockRecv](#)
- [SockRecvFrom](#)
- [SockSelect](#)
- [SockSend](#)
- [SockSendTo](#)
- [SockSetSockOpt](#)
- [SockShutDown](#)
- [SockSock_Erno](#)
- [SockSocket](#)
- [SockSoClose](#)

5.1. SockLoadFuncs

The SockLoadFuncs() call loads all RxSock functions.

Syntax:

```
>>--SockLoadFuncs(--+-----+--)------><
                        +--parm--+
```

All parameters that you supply are only used to bypass copyright information.

5.2. SockDropFuncs

The SockDropFuncs call drops all RxSock functions.

Syntax:

```
SockDropFuncs()
```

To unload the dynamic load library (DLL), first call SockDropFuncs() and then exit all CMD.EXE shells. After exiting all command shells, the DLL is dropped by the system and can be deleted or replaced.

5.3. SockVersion

The SockVersion() call provides the version of RxSock.

Syntax:

```
>>--SockVersion()------><
```

Return Values:

The returned value is in the form version.subversion, for example 2.1.

Prior to Version 1.2, this function did not exist. To check if a former version of Rxsock is installed, use the following code after loading the function package with SockLoadFuncs():

```
/* oldVersion is 1 if a version of RxSock < 1.2 is loaded */
oldVersion = (1 = RxFuncQuery("SockVersion"))
```

5.4. SockAccept

The SockAccept() call accepts a connection request from a remote host.

Syntax:

```
>>--SockAccept(socket--+-----+--)------><
                        +--, address--+
```

where:

socket

is the socket descriptor created with the `SocketSocket()` call. It is bound to an address using the `SocketBind()` call and must be enabled to accept connections using the `SocketListen()` call.

address

is a stem variable that contains the socket address of the connection client when the `SocketAccept()` call returns. This parameter is optional.

`SocketAccept()` is used by a server in a connection-oriented mode to accept a connection request from a client. The call accepts the first connection on its queue of pending connection requests. It creates a new socket descriptor with the same properties as `socket` and returns it to the caller. This new socket descriptor cannot be used to accept new connections. Only the original socket can accept more connection requests.

If the queue has no pending connection requests, `SocketAccept()` blocks the caller unless the socket is in nonblocking mode. If no connection requests are queued and the socket is in nonblocking mode, `SocketAccept()` returns a value of -1 and sets the return code to the value `EWouldBlock`.

You cannot get information on requesters without calling `SocketAccept()`. The application cannot tell the system from which requesters it will accept connections. The caller can close a connection immediately after identifying the requester.

The `SocketSelect()` call can be used to check the socket for incoming connection requests.

Return Values:

A positive value indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code by calling `SocketErrno()` or `SocketPSockErrno()`. Possible values:

ENOTSOCK

socket is not a valid socket descriptor.

EINTR

Interrupted system call.

EINVAL

`SocketListen()` was not called for socket.

EOPNOTSUPP

socket is not connection-oriented.

EWouldBlock

socket is in nonblocking mode, and there are no connection requests queued.

ECONNABORTED

The software caused a connection close.

Note: SockAccept() interfaces with the C function accept().

5.5. SockBind

The SockBind() call binds a local name to the socket.

Syntax:

```
>>--SockBind(socket, address)-----><
```

where:

socket

is the socket descriptor returned by a previous call to SockSocket().

address

is a stem variable containing the address that is to be bound to socket.

SockBind() binds the unique local name address to the socket with descriptor socket. After calling SockSocket(), a descriptor does not have a name. However, it belongs to a particular address family that you specified when calling SockSocket().

Because socket was created in the AF_INET domain, the fields of the stem address are as follows:

The family field must be set to AF_INET. The port field is set to the port to which the application must bind. If port is set to 0, the caller allows the system to assign an available port. The application can call SockGetSockName() to discover the port number assigned. The addr field is set to the Internet address. On hosts with more than one network interface (called multihomed hosts), a caller can select the interface with which it is to bind.

Only UDP packets and TCP connection requests from this interface that match the bound name are routed to the application. This is important when a server offers a service to several networks. If addr is set to INADDR_ANY, the caller requests socket be bound to all network interfaces on the host. If you do not specify an address, the server can accept all UDP packets and TCP connection requests made to its port, regardless of the network interface on which the requests arrived.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code by calling SockSock_Errno() or SockPSock_Errno(). Possible values:

EADDRINUSE

address is already in use. See the SO_REUSEADDR option described under SockGetSockOpt() and the SO_REUSEADDR option described under SockSetSockOpt().

EADDRNOTAVAIL

The address specified is not valid on this host. For example, the Internet address does not specify a valid network interface.

EAFNOSUPPORT

The address family is not supported.

ENOTSOCK

socket is not a valid socket descriptor.

EINVAL

socket is already bound to an address.

ENOBUFS

No buffer space available.

Note: SockBind() interfaces with the C function bind().

5.6. SockClose

The SockClose() call shuts down a socket and frees resources allocated to the socket.

Syntax

```
>>--SockClose(socket)-----><
```

where:

socket

is the descriptor of the socket to be closed.

If the SO_LINGER option of SockSetSockOpt() is enabled, any queued data is sent. If this option is disabled, any queued data is flushed.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code by calling SockSock_Errno() or SockPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EALREADY

The socket is in nonblocking mode. A previous connection attempt has not completed.

SockClose() is exactly the same as SockSoClose().

Note: SockClose() interfaces with the C function soclose() or, in the Windows environments, with closesocket().

5.7. SockConnect

The SockConnect() socket call requests a connection to a remote host.

Syntax:

```
>>--SockConnect(socket, address)-----><
```

where:

socket

is the socket descriptor used to issue the connection request.

address

is a stem variable containing the address of the socket to which a connection is to be established.

The SockConnect() call performs the following tasks when called for a stream socket:

1. It completes the binding for a socket, if necessary.
2. It attempts to create a connection between two sockets.

This call is used by the client side of socket-based applications to establish a connection with a server. The remote server must have a passive open pending, which means it must successfully call SockBind() and SockListen(). Otherwise, SockConnect() returns the value -1 and the error value is set to ECONNREFUSED.

In the Internet communication domain, a timeout occurs if a connection to the remote host is not established within 75 seconds.

If the socket is in blocking mode, the SockConnect() call blocks the caller until the connection is established or an error is received. If the socket is in nonblocking mode, SockConnect() returns the value -1 and sets the error value to EINPROGRESS if the connection was successfully initiated. The caller can test the completion of the connection by calling:

- SockSelect(), to test for the ability to write to the socket
- SockGetsockopt(), with option SO_ERROR, to test if the connection was established

Stream sockets can call SockConnect() only once.

Datagram or raw sockets normally transfer data without being connected to the sender or receiver. However, an application can connect to such a socket by calling SockConnect(). SockConnect() specifies and stores the destination peer address for the socket. The system then knows to which address to send data and the destination peer address does not have to be specified for each datagram sent. The address is kept until the next SockConnect() call. This permits the use of the SockRecv() and SockSend() calls, which are usually reserved for connection-oriented sockets. However, data is still not necessarily delivered, which means the normal features of sockets using connectionless data transfer are maintained. The application can therefore still use the SockSendTo() and SockRecvFrom() calls.

Datagram and raw sockets can call SockConnect() several times. The application can change their destination address by specifying a new address on the SockConnect() call. In addition, the socket can be returned to a connectionless mode by calling SockConnect() with a null destination address. The null

address is created by setting the stem variable address as follows: the family field to AF_INET, the port field to 0, and the addr field to 0.0.0.0.

The call to SockConnect returns the value -1, indicating that the connection to the null address cannot be established. Calling SockSock_Erno() returns the value EADDRNOTAVAIL.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code by calling SockSock_Erno() or SockPSock_Erno(). Possible values are:

EADDRNOTAVAIL

The calling host cannot reach the specified destination.

EAFNOSUPPORT

The address family is not supported.

EALREADY

The socket is in nonblocking mode. A previous connection attempt has not completed.

ENOTSOCK

The socket is not a valid socket descriptor.

ECONNREFUSED

The destination host rejected the connection request.

EINPROGRESS

socket is in nonblocking mode, and the connection cannot be completed immediately.
EINPROGRESS does not indicate an error.

EINTR

Interrupted system call.

EISCONN

socket is already connected.

ENETUNREACH

The network cannot be reached from this host.

ETIMEDOUT

Establishing the connection timed out.

ENOBUFS

There is no buffer space available.

EOPNOTSUPP

The operation is not supported on socket.

Note: SockConnect interfaces with the C function connect().

5.8. SockGetHostByAddr

The SockGetHostByAddr() call retrieves information about a specific host using its address.

Syntax:

```
>>--SockGetHostByAddr(dotAddress, host--+-----+--)------><
                                +--, domain--+
```

where:

dotAddress

is the standard dotted decimal address of the host.

host

is a stem variable that is to receive the information on the host.

domain

is the domain AF_INET. This parameter is optional.

Return values:

The value 1 indicates successful execution of the call. The value 0 indicates an error.

Note: SockGetHostByAddress() interfaces with the C function gethostbyaddr().

5.9. SockGetHostByName

The SockGetHostByName() call retrieves host information on a specific host using its name or any alias.

Syntax:

```
>>--SockGetHostByName(nameAddress, host)------><
```

where:

nameAddress

is the name of a host, for example www.ibm.com.

host

is the name of a stem variable to receive the information on the host.

Return values:

The value 1 indicates successful execution of the call. The value 0 indicates an error.

Note: SockGetHostByName() interfaces with the C function gethostbyname().

5.10. SockGetHostId

The SockGetHostId() call retrieves the dotAddress of the local host.

Syntax:

```
>>--SockGetHostId()-----><
```

The return value is the dotAddress of the local host.

Note: SockGetHostId() interfaces with the C function gethostid().

5.11. SockGetPeerName

The SockGetPeerName() call gets the name of the peer connected to a socket.

Syntax:

```
>>--SockGetPeerName(socket, address)-----><
```

where:

socket

is the socket descriptor.

address

is a stem variable that will contain the address of the peer connected to socket.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code by calling SockSock_Errno() or SockPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

ENOTCONN

socket is not connected.

ENOBUFS

There is no buffer space available.

Note: SockGetPeerName() interfaces with the C function getpeername().

5.12. SockGetSockName

The SockGetSockName() call gets the local socket name.

Syntax:

```
>>--SockGetSockName(socket, address)-----><
```

where:

socket

is the socket descriptor.

address

is a stem variable that is to receive the address of the socket returned.

SockGetSockName() returns the address for socket in the stem variable address. If the socket is not bound to an address, the call returns a null address.

The returned null address is a stem variable with the family field set to AF_INET, the port field set to 0, and the addr field set to 0.0.0.0.

All sockets are explicitly assigned an address after a successful call to SockBind(). Stream sockets are implicitly assigned an address after a successful call to SockConnect() or SockAccept() if SockBind() was not called.

The SockGetSockName() call is often used to identify the port assigned to a socket after the socket has been implicitly bound to a port. For example, an application can call SockConnect() without previously calling SockBind(). In this case, the SockConnect() call completes the binding necessary by assigning a port to the socket.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code by calling SockSock_Erno() or SockPSock_Erno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

ENOBUFS

There is no buffer space available.

Note: SockGetSockName() interfaces with the C function getsockname().

5.13. SockGetSockOpt

The SockGetSockOpt() call gets the socket options associated with a socket.

Syntax:

```
>>--SockGetSockOpt(socket, level, optName, optVal)-----><
```

where:

socket

is the socket descriptor.

level

specifies which option level is queried for the specified optname. The only supported level is SOL_SOCKET.

optname

is the name of the specified socket option. Only one option can be specified with a call.

optval

is the variable to receive the option values requested. For socket options that are Boolean the option is enabled if optval is nonzero and disabled if optval is 0.

SockGetSockOpt() returns the value of a socket option at the socket level. It can be requested for sockets of all domain types. Some options are supported only for specific socket types.

The following options are recognized for SOL_SOCKET:

SO_BROADCAST

returns the information whether datagram sockets are able to broadcast messages. If this option is enabled, the application can send broadcast messages using datagram socket, if the interface specified in the destination supports broadcasting of packets.

SO_DEBUG

returns the information whether debug information can be recorded for a socket.

SO_DONTROUTE

returns the information whether the socket is able to bypass the routing of outgoing messages. If this option is enabled, outgoing messages are directed to the network interface specified in the network portion of the destination address. When enabled, packets can only be sent to directly connected networks.

SO_ERROR

returns any error pending at the socket and clears the error status. It can be used to check for asynchronous errors at connected datagram sockets or for asynchronous errors that are not explicitly returned by one of the socket calls.

SO_KEEPALIVE

returns the information whether stream sockets are able to send keepalive packets. TCP uses a timer called the keepalive timer. This timer monitors idle connections that might have been disconnected because of a peer crash or timeout. If this option is enabled, a keepalive packet is periodically sent to the peer.

This option is mainly used to enable servers to close connections that are no longer active as a result of clients ending connections without properly closing them.

SO_LINGER

returns the information whether stream sockets are able to linger on close if data is present. If this option is enabled and there is data still to be sent when `SocketClose()` is called, the calling application is blocked during the `SocketClose()` call until the data is transmitted or the connection has timed out. If this option is disabled, the `SocketClose()` call returns without blocking the caller while TCP is trying to send the data. Although the data transfer is usually successful, it cannot be guaranteed because TCP tries to send the data only for a specific amount of time.

SO_OOBINLINE

returns the information whether stream sockets are able to receive out-of-band data. If this option is enabled, out-of-band data is placed in the normal data input queue as it is received. It is then made available to `SocketRecv()` and `SocketRecvFrom()` without the `MSG_OOB` flag being specified in those calls. If this option is disabled, out-of-band data is placed in the priority data input queue as it is received. It can then only be made available to `SocketRecv()` and `SocketRecvFrom()` by specifying the `MSG_OOB` flag in those calls.

SO_RCVBUF

returns the buffer size for input.

SO_RCVLOWAT

returns the receive low-water mark.

SO_RCVTIMEO

returns the timeout value for a receive operation.

SO_REUSEADDR

returns the information whether stream and datagram sockets are able to reuse local addresses. If this option is enabled, the local addresses that are already in use can then be bound. This alters the normal algorithm used in the `SocketBind()` call. At connection time, the system checks whether the local addresses and ports differ from foreign addresses and ports. If not, the error value `EADDRINUSE` is returned.

SO_SNDBUF

returns the size of the send buffer.

SO_SNDLOWAT

returns the send low-water mark. This mark is ignored for nonblocking calls and not used in the Internet domain.

SO_SNDTIMEO

returns the timeout value for a send operation.

SO_TYPE

returns the socket type. The integer pointed to by `optval` is then set to one of the following: `STREAM`, `DGRAM`, `RAW`, or `UNKNOWN`.

SO_USELOOPBACK

bypasses hardware where possible.

All option values are integral except for `SO_LINGER`, which contains the following blank-delimited integers:

- The `l_onoff` value. It is set to 0 if the `SO_LINGER` option is disabled.
- The `l_linger` value. It specifies the amount of time, in seconds, to be lingered on close. A value of 0 causes `SocketSoClose()` to wait until disconnection completes.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code by calling `SocketErrno()` or `SocketPSock_Errno()`. Possible values are:

EADDRINUSE

The address is already in use.

ENOTSOCK

socket is not a valid socket descriptor.

ENOPROTOPT

`optname` or level is not recognized.

Note: `SocketGetSockOpt()` interfaces with the C function `getsockopt()`.

5.14. SockInit

The SockInit() call initializes the socket data structures and checks whether the TCP/IP network is active.

Syntax:

```
>>--SockInit()-----><
```

SockInit() can be called at the beginning of each program that uses SockSocket(). However, it is not obligatory because each RxSock function is automatically initialized. For this reason, explicit initialization is not available in all system environments.

Return values:

The value 0 indicates successful execution of the call. The value 1 indicates an error.

Note: SockInit() interfaces with the C function `sock_init()`.

5.15. SockIoctl

The SockIoctl() call performs special operations on the socket.

Syntax:

```
>>--SockIoctl(socket, ioctlCmd, ioctlData)-----><
```

where:

socket

is the socket descriptor.

ioctlCmd

is the ioctl command to be performed.

ioctlData

is a variable containing data associated with the particular command. Its format depends on the command requested. Valid commands are:

FIONBIO

sets or clears nonblocking input or output for a socket. This command is an integer. If the integer is 0, nonblocking input or output on the socket is cleared. If the integer is a number other than 0, input or output calls do not block until the call is completed.

FIONREAD

gets the number of immediately readable bytes for the socket. This command is an integer.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code `Socket_Sock_Errno()` or `Socket_PSock_Errno()`. Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EINVAL

The request is not valid or not supported.

EOPNOTSUPP

The operation is not supported on the socket.

Note: `SocketIoctl()` interfaces with the C function `ioctl()` or, in the Windows environments, with `ioctlsocket()`.

5.16. SockListen

The `SocketListen()` call completes the binding necessary for a socket to accept connections and creates a connection request queue for incoming requests.

Syntax:

```
>>--SocketListen(socket, backlog)-----><
```

where:

`socket`

is the socket descriptor.

`backlog`

controls the maximum queue length for pending connections.

`SocketListen()` performs the following tasks:

1. It completes the binding necessary for `socket`, if `SocketBind()` has not been called for the socket.
2. It creates a connection request queue with a length of `backlog` to queue incoming connection requests.

When the queue is full, additional connection requests are ignored.

`SocketListen()` can only be called for connection-oriented sockets.

`SocketListen()` is called after allocating a socket with `SocketSocket()` and after binding a name to socket with `SocketBind()`. It must be called before `SocketAccept()`.

SocketListen() indicates when it is ready to accept client connection requests. It transforms an active socket to a passive socket. After it is called, socket cannot be used as an active socket to initiate connection requests.

If backlog is smaller than 0, SocketListen() interprets the backlog to be 0. If it is greater than the maximum value defined by the network system, SocketListen() interprets the backlog to be this maximum value.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code SocketSock_Errno() or SocketPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EOPNOTSUPP

socket is not a socket descriptor that supports the SocketListen() call.

Note: SocketListen() interfaces with the C function listen().

5.17. SocketPSock_Errno

The SocketPSock_Errno() call writes a short error message to the standard error device. It describes the last error encountered during a call to a socket library function.

Syntax:

```
>>--SocketPSock_Errno(--+-----+--)------><
                        +--error_string--+
```

where:

error_string

is the error string written to the standard error device describing the last error encountered. The string printed is followed by a colon, a space, and then the message. If it is omitted or empty, only the message is printed. The string is optional.

The error code is acquired by calling SocketSock_Errno(). It is set when errors occur. Subsequent socket calls do not clear the error code.

Note: SocketPSock_Errno() interfaces with the C function psock_errno().

5.18. SockRecv

The SockRecv() call receives data on a connected socket.

Syntax:

```
>>--SockRecv(socket, var, len--++-----+--)------><
                                +--, flags--+
```

where:

socket

is the socket descriptor.

var

is the name of a Rexx variable to receive the data.

len

is the maximum amount of data to be read.

flags

is a blank-delimited list of options:

MSG_OOB

reads any out-of-band data on the socket.

MSG_PEEK

peeks at the data on the socket. The data is returned but not removed, so the subsequent receive operation sees the same data.

SockRecv() receives data on a socket with descriptor socket and stores it in the Rexx variable var. It applies only to connected sockets. For information on how to use SockRecv() with datagram and raw sockets, see Datagram or raw sockets.

SockRecv() returns the length of the incoming data. If a datagram is too long to fit the buffer, the excessive data is discarded. No data is discarded for stream sockets. If data is not available at socket, the SockRecv() call waits for a message and blocks the caller unless the socket is in nonblocking mode. See SockIoctl() for a description of how to set the nonblocking mode.

Return values:

If successful, the length of the data in bytes is returned. The value 0 indicates that the connection is closed. The value -1 indicates an error. You can get the specific error code SockSock_Errno() or SockPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EINTR

Interrupted system call.

EINVAL

Invalid argument.

EWouldBlock

socket is in nonblocking mode and no data is available, or the SO_RCVTIMEO option has been set for socket and the timeout expired before any data arrived.

Note: SockRecv() interfaces to the C function recv().

5.19. SockRecvFrom

The SockRecvFrom() call receives data on a socket.

Syntax:

```
>>--SockRecvFrom(socket, var, len--+-----+--, address)-----><
                                +--, flags--+
```

where:

socket

is the socket descriptor.

var

is the name of a Rexx variable to receive the data.

len

is the maximum amount of data to be read.

flags

is a blank delimited list of options:

MSG_OOB

reads any out-of-band data on the socket.

MSG_PEEK

peeks at the data present on the socket. The data is returned but not consumed. The subsequent receive operation thus sees the same data.

address

is a stem variable specifying the address of the sender from which the data is received, unless it is a null address.

SockRecvFrom() receives data on a socket with descriptor socket and stores it in a Rexx variable named var. It applies to any socket type, whether connected or not.

SockRecvFrom() returns the length of the incoming message or data. If a datagram is too long to fit the supplied buffer, the excessive data is discarded. No data is discarded for stream sockets. If data is not available at socket, the SockRecvFrom() call waits for a message to arrive and blocks the caller, unless the socket is in nonblocking mode. See SockIoctl() for a description of how to set the nonblocking mode.

Return values:

If successful, the length of the data in bytes is returned. The value -1 indicates an error. You can get the specific error code SockSock_Errno() or SockPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EINVAL

Invalid argument.

EWOULDBLOCK

socket is in nonblocking mode, no data is available, or the SO_RCVTIMEO option has been set for socket and the timeout expired before data arrived.

Note: SockRecvFrom() interfaces with the C function recvfrom().

5.20. SockSelect

The SockSelect() call monitors the activity on a socket with regard to readability, readiness for writing, and pending exceptional conditions.

Syntax:

```
>>--SockSelect(reads, writes, excepts--+-----+--)------><
                                +--, timeout--+
```

where:

reads

is the number of sockets to be checked for readability.

writes

is the number of sockets to be checked for readiness for writing.

excepts

is the number of sockets to be checked for pending exceptional conditions. For Network Services sockets, the only pending exceptional condition is out-of-band data in the receive buffer.

timeout

is the maximum number of seconds the system waits for the selection to complete. Set the timeout parameter to 0 for a blocking operation. If the socket is ready, the return will be immediate.

Each parameter specifying a number of sockets is qualified by a stem variable which is queried and set by this function. The stem variable has the following format: stem.0 contains the number of sockets, stem.1 the first socket, and so on. Upon return, the stem variables are reset to the sockets that are ready. If any of the stem variables are empty (), or no parameter is passed, no sockets for that type are checked.

The timeout value must be integral (no fractional values). Nonnumeric and negative numbers are considered to be 0. If no timeout value is passed, an empty string () is assumed.

If the timeout value is 0, SockSelect() does not wait before returning. If the timeout value is an empty string (), SockSelect() does not time out, but returns when a socket becomes ready. If the timeout value is in seconds, SockSelect() waits for the specified interval before returning. It checks all indicated sockets at the same time and returns as soon as one of them is ready.

Return values:

The number of ready sockets is returned. The value 0 indicates an expired time limit. In this case, the stem variables are not modified. The value -1 indicates an error. You can get the specific error code SockSock_Errno() or SockPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EFAULT

The address is not valid.

EINVAL

Invalid argument.

EINTR

Interrupted system call.

Examples:

```

r.0 = 2                /* specify 2 sockets for read in stem r. */
r.1 = 101
r.2 = 102

                        /* specify 1 socket for write in stem w. */
w.0 = 1
w.1 = 103

                        /* no sockets for exceptions in stem e. */
e.0 = 0
rc = SockSelect("r.", "w.", "e.")
do i = 1 to r.0        /* display sockets ready for read */

```

```

    say "socket" r.i "is ready for reading."
end

```

That SockSelect() call can be invoked as:

```
rc = SockSelect("r.", "w.", "")
```

or

```
rc = SockSelect("r.", "w.", )
```

The function call SockSelect(, , x) results in the program pausing for x seconds.

Note: SockSelect() interfaces with the C function select().

5.21. SockSend

The SockSend() call sends data to a connected socket.

Syntax:

```

>>--SockSend(socket, data--+-----+--)-><
                                +--, flags--+

```

where:

socket

is the socket descriptor.

data

is the name of a Rexx variable containing the data to be transmitted.

flags

is a blank delimited list of options:

MSG_OOB

sends out-of-band data to sockets that support SOCK_STREAM communication.

MSG_DONTROUTE

turns on the SO_DONTROUTE option for the duration of the send operation. This option is usually only used by diagnostic or routing programs.

SockSend() sends data to a connected socket with descriptor socket. For information on how to use SockSend() with datagram and raw sockets, see Datagram or raw sockets.

If the socket does not have enough buffer space to hold the data to be sent, the `SocketSend()` call blocks unless the socket is placed in nonblocking mode. See `SocketIoctl()` for a description of how to set the nonblocking mode. Use the `SocketSelect()` call to determine when it is possible to send more data.

Return values:

If successful, the number of bytes of the socket with descriptor `socket` that is added to the send buffer is returned. Successful completion does not imply that the data has already been delivered to the receiver.

The return value -1 indicates that an error was detected on the sending side of the connection. You can get the specific error code `SocketErrno()` or `SocketPsock_Errno()`. Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EINTR

Interrupted system call.

EINVAL

Invalid argument.

ENOBUFS

There is no buffer space available to send the message.

EWOULDBLOCK

socket is in nonblocking mode, the data cannot be sent without blocking, or the `SO_SNDTIMEO` option has been set for socket and the timeout expired before any data was sent.

Note: `SocketSend()` interfaces with the C function `send()`.

5.22. SocketSendTo

The `SocketSendTo()` call sends data to a connected or unconnected socket.

Syntax:

```
>>--SocketSendTo(socket, data--+-----+--, address)-----><
                        +--, flags--+
```

where:

`socket`

is the socket descriptor.

`data`

is a string of data to be transmitted.

flags

is a blank delimited list of options:

MSG_OOB

sends out-of-band data to sockets that support SOCK_STREAM communication.

MSG_DONTROUTE

turns on the SO_DONTROUTE option for the duration of the send operation. This option is usually only used by diagnostic or routing programs.

address

is a stem variable containing the destination address.

SockSendTo() sends data to a connected or unconnected socket with descriptor socket. For unconnected datagram and raw sockets, it sends data to the specified destination address. For stream sockets, the destination address is ignored.

Datagram sockets are connected by calling SockConnect(). This call identifies the peer to send or receive the datagram. After a datagram socket is connected to a peer, you can still use the SockSendTo() call but you cannot include a destination address.

To change the peer address when using connected datagram sockets, issue SockConnect() with a null address. Specifying a null address removes the peer address specification. You can then issue either a SockSendTo() call and specify a different destination address or a SockConnect() call to connect to a different peer. For more information on connecting datagram sockets and specifying null addresses, see Datagram or raw sockets.

Return values:

If successful, the number of bytes sent is returned. Successful completion does not guarantee that the data is delivered to the receiver. The return value -1 indicates that an error was detected on the sending side. You can get the specific error code SockSock_Errno() or SockPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EMSGSIZE

The message data was too big to be sent as a single datagram.

ENOBUFS

There is no buffer space available to send the message.

EWouldBlock

socket is in nonblocking mode, the data cannot be sent without blocking, or the SO_SNDTIMEO option has been set for socket and the timeout expired before any data was sent.

ENOTCONN

The socket is not connected.

EDESTADDRREQ

Destination address required.

Note: SockSendTo() interfaces with the C function sendto().

5.23. SockSetSockOpt

The SockSetSockOpt() call sets options associated with a socket.

Syntax:

```
>>--SockSetSockOpt(socket, level, optName, optVal)-----><
```

where:

socket

is the socket descriptor.

level

specifies which option level is set. The only supported level is SOL_SOCKET.

optname

is the name of a specified socket option.

optval

is the variable containing the data needed by the set command. It is optional.

SockSetSockOpt() sets options associated with a socket with descriptor socket such as enabling debugging at the socket or protocol level, controlling timeouts, or permitting socket data broadcasting. Options can exist at the socket or the protocol level. They are always present at the highest socket level. When setting socket options, the option level and name must be specified.

For socket options that are toggles, the option is enabled if optval is nonzero and disabled if optval is 0.

The following options are recognized for SOL_SOCKET:

SO_BROADCAST

enables datagram sockets to broadcast messages. The application can then send broadcast messages using datagram socket, if the interface specified in the destination supports broadcasting of packets.

SO_DEBUG

enables debug information to be recorded for a socket.

SO_DONTROUTE

enables the socket to bypass the routing of outgoing messages. Outgoing messages are then directed to the network interface specified in the network portion of the destination address. When enabled, packets can only be sent to directly connected networks.

SO_KEEPALIVE

enables stream sockets to send keepalive packets, which keep the connection alive. TCP uses a timer called the keepalive timer. This timer monitors idle connections that might have been disconnected because of a peer crash or timeout. If this option is enabled, a keepalive packet is periodically sent to the peer.

This option is mainly used to enable servers to close connections that are no longer active as a result of clients ending connections without properly closing them.

SO_LINGER

enables stream sockets to linger on close if data is present. If this option is enabled and there is data still to be sent when `SocketClose()` is called, the calling application is blocked during the `SocketClose()` call until the data is transmitted or the connection has timed out. If this option is disabled, the `SocketClose()` call returns without blocking the caller while TCP is trying to send the data. Although the data transfer is usually successful, it cannot be guaranteed because TCP tries to send the data only for a specific amount of time.

SO_OOBINLINE

enables stream sockets to receive out-of-band data, which is a logically separate data path using the same connection as the normal data path. If this option is enabled, out-of-band data is placed in the normal data input queue as it is received. It is then made available to `SocketRecv()` and `SocketRecvFrom()` without the `MSG_OOB` flag being specified in those calls. If this option is disabled, out-of-band data is placed in the priority data input queue as it is received. It can then only be made available to `SocketRecv()` and `SocketRecvFrom()` by specifying the `MSG_OOB` flag in those calls.

SO_RCVBUF

sets the buffer size for input. This option sets the size of the receive buffer to the value contained in the buffer pointed to by `optval`. In this way, the buffer size can be tailored for specific application needs, such as increasing the buffer size for high-volume connections.

SO_RCVLOWAT

sets the receive low-water mark.

SO_RCVTIMEO

sets the timeout value for a receive operation.

SO_REUSEADDR

enables stream and datagram sockets to reuse local addresses. Local addresses that are already in use can then be bound. This alters the normal algorithm used in the `SocketBind()` call. At connection time, the system checks whether the local addresses and ports differ from foreign addresses and ports. If not, the error value `EADDRINUSE` is returned.

SO_SNDBUF

Sets the buffer size for output. This option sets the size of the send buffer to the value contained in the buffer pointed to by `optval`. In this way, the send buffer size can be tailored for specific application needs, such as increasing the buffer size for high-volume connections.

SO_SNDLOWAT

sets the send low-water mark. This mark is ignored for nonblocking calls and not used in the Internet domain.

SO_SNDTIMEO

sets the timeout value for a send operation.

SO_USELOOPBACK

bypasses hardware where possible.

Except for `SO_LINGER`, all values are integral. `SO_LINGER` expects two blank delimited integers:

1. The `l_onoff` value. It is set to 0 if the `SO_LINGER` option is disabled.
2. the `l_linger` value. The `l_linger` field specifies the amount of time, in seconds, to be lingered on close. A value of 0 causes `SocketClose()` to wait until disconnection completes.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code `SocketErrno()` or `SocketPSockErrno()`. Possible values are:

EADDRINUSE

The address is already in use.

ENOTSOCK

socket is not a valid socket descriptor.

ENOPROTOOPT

`optname` is not recognized.

EINVAL

Invalid argument.

ENOBUFS

There is no buffer space available.

Note: `SocketSetSockOpt()` interfaces with the C function `setsockopt()`.

5.24. SockShutDown

The SockShutDown() call shuts down all, or part, of a full duplex connection. This call is optional.

Syntax:

```
>>--SockShutDown(socket, howto)-----><
```

>where:

socket

is the socket descriptor.

howto

is the condition of the shutdown of socket.

Because data flows in different directions are independent of each other, SockShutDown() allows you to independently stop data flows in one direction, or all data flows, with one API call. For example, you can enable yourself to send data but disable other senders to send data to you.

The howto parameter sets the condition for shutting down the connection to socket socket. It can be set to one of the following:

0

No more data can be received on socket.

1

No more output is allowed on socket.

2

No more data can be sent or received on socket.

Return values:

The value 0 indicates successful execution of the call. The value -1 indicates an error. You can get the specific error code SockSock_Errno() or SockPSock_Errno(). Possible values are:

ENOTSOCK

socket is not a valid socket descriptor.

EINVAL

howto was not set to a valid value.

Note: SockShutDown() interfaces with the C function shutdown().

5.25. SockSock_Errno

The SockSock_Errno() call returns the last error code set by a socket call. Subsequent socket API calls do not reset this error code.

Syntax:

```
>>--SockSock_Errno()-----><
```

Note: SockSock_Errno() interfaces with the C function sock_errno().

5.26. SockSocket

The SockSocket() call creates an end point for communication and returns a socket descriptor representing the end point. Each socket type provides a different communication service.

Syntax:

```
>>--SockSocket(domain, type, protocol)-----><
```

where:

domain

is the communication domain requested. It specifies the protocol family to be used. Currently, only the domain AF_INET is supported, which uses addresses in the Internet address format.

type

is the type of socket created. The following types are supported:

SOCK_STREAM

provides sequenced, two-way byte streams that are reliable and connection-oriented. It supports a mechanism for out-of-band data. Stream sockets are supported by the Internet (AF_INET) communication domain.

SOCK_DGRAM

provides datagrams, which are connectionless messages of a fixed length whose reliability is not guaranteed. Datagrams can be received out of order, lost, or delivered several times. Datagram sockets are supported by the Internet (AF_INET) communication domain.

SOCK_RAW

provides the interface to internal protocols, such as IP and ICMP. Raw sockets are supported by the Internet (AF_INET) communication domain.

protocol

is the protocol to be used with the socket. It can be IPPROTO_UDP, IPPROTO_TCP, or 0. If it is set to 0, which is the default, the system selects the default protocol number for the domain and socket type requested.

Sockets are deallocated with the SockClose() call.

Return values:

A non-negative socket descriptor return value indicates successful execution of the call. The return value -1 indicates an error. You can get the specific error code SockSock_Errno() or SockPSock_Errno().

Possible values are:

EMFILE

The maximum number of sockets are currently in use.

EPROTONOSUPPORT

The protocol is not supported in the specified domain or the protocol is not supported for the specified socket type.

EPFNOSUPPORT

The protocol family is not supported.

ESOCKTNOSUPPORT

The socket type is not supported.

Note: SockSocket() interfaces with the C function socket().

5.27. SockSoClose

The SockSoClose() call shuts down a socket and frees resources allocated to the socket.

Syntax:

```
>>--SockSoClose(socket)-----><
```

where:

socket

is the socket descriptor of the socket to be closed.

This function is identical to SockClose().

Appendix A. Notices

Any reference to a non-open source product, program, or service is not intended to state or imply that only non-open source product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any Rexx Language Association (RexxLA) intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-open source product, program, or service.

Any performance data contained herein was determined in a controlled environment. Therefore, the results obtained in other operating environments may vary significantly. Some measurements may have been made on development-level systems and there is no guarantee that these measurements will be the same on generally available systems. Furthermore, some measurement may have been estimated through extrapolation. Actual results may vary. Users of this document should verify the applicable data for their specific environment.

Information concerning non-open source products was obtained from the suppliers of those products, their published announcements or other publicly available sources. RexxLA has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-RexxLA packages. Questions on the capabilities of non-RexxLA packages should be addressed to the suppliers of those products.

All statements regarding RexxLA's future direction or intent are subject to change or withdrawal without notice, and represent goals and objectives only.

This information contains examples of data and reports used in daily business operations. To illustrate them as completely as possible, the examples include the names of individuals, companies, brands, and products. All of these names are fictitious and any similarity to the names and addresses used by an actual business enterprise is entirely coincidental.

A.1. Trademarks

Open Object Rexx™ and ooRexx™ are trademarks of the Rexx Language Association.

The following terms are trademarks of the IBM Corporation in the United States, other countries, or both:

1-2-3
AIX
IBM
Lotus
OS/2
S/390
VisualAge

AMD is a trademark of Advance Micro Devices, Inc.

Intel, Intel Inside (logos), MMX and Pentium are trademarks of Intel Corporation in the United States, other countries, or both.

Java and all Java-based trademarks are trademarks of Sun Microsystems, Inc. in the United States, other countries, or both.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Microsoft, Windows, Windows NT, and the Windows logo are trademarks of Microsoft Corporation in

the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Other company, product, or service names may be trademarks or service marks of others.

A.2. Source Code For This Document

The source code for this document is available under the terms of the Common Public License v1.0 which accompanies this distribution and is available in the appendix [Common Public License Version 1.0](#). The source code itself is available at

http://sourceforge.net/project/showfiles.php?group_id=119701.

The source code for this document is maintained in DocBook SGML/XML format.



Appendix B. Common Public License Version 1.0

THE ACCOMPANYING PROGRAM IS PROVIDED UNDER THE TERMS OF THIS COMMON PUBLIC LICENSE ("AGREEMENT"). ANY USE, REPRODUCTION OR DISTRIBUTION OF THE PROGRAM CONSTITUTES RECIPIENT'S ACCEPTANCE OF THIS AGREEMENT.

B.1. Definitions

"Contribution" means:

1. in the case of the initial Contributor, the initial code and documentation distributed under this Agreement, and
2. in the case of each subsequent Contributor:
 - a. changes to the Program, and
 - b. additions to the Program;

where such changes and/or additions to the Program originate from and are distributed by that particular Contributor. A Contribution 'originates' from a Contributor if it was added to the Program by such Contributor itself or anyone acting on such Contributor's behalf. Contributions do not include additions to the Program which: (i) are separate modules of software distributed in conjunction with the Program under their own license agreement, and (ii) are not derivative works of the Program.

"Contributor" means any person or entity that distributes the Program.

"Licensed Patents " mean patent claims licensable by a Contributor which are necessarily infringed by the use or sale of its Contribution alone or when combined with the Program.

"Program" means the Contributions distributed in accordance with this Agreement.

"Recipient" means anyone who receives the Program under this Agreement, including all Contributors.

B.2. Grant of Rights

1. Subject to the terms of this Agreement, each Contributor hereby grants Recipient a non-exclusive, worldwide, royalty-free copyright license to reproduce, prepare derivative works of, publicly display, publicly perform, distribute and sublicense the Contribution of such Contributor, if any, and such derivative works, in source code and object code form.
2. Subject to the terms of this Agreement, each Contributor hereby grants Recipient a non-exclusive, worldwide, royalty-free patent license under Licensed Patents to make, use, sell, offer to sell, import and otherwise transfer the Contribution of such Contributor, if any, in source code and object code form. This patent license shall apply to the combination of the Contribution and the Program if, at the time the Contribution is added by the Contributor, such addition of the Contribution causes such

combination to be covered by the Licensed Patents. The patent license shall not apply to any other combinations which include the Contribution. No hardware per se is licensed hereunder.

3. Recipient understands that although each Contributor grants the licenses to its Contributions set forth herein, no assurances are provided by any Contributor that the Program does not infringe the patent or other intellectual property rights of any other entity. Each Contributor disclaims any liability to Recipient for claims brought by any other entity based on infringement of intellectual property rights or otherwise. As a condition to exercising the rights and licenses granted hereunder, each Recipient hereby assumes sole responsibility to secure any other intellectual property rights needed, if any. For example, if a third party patent license is required to allow Recipient to distribute the Program, it is Recipient's responsibility to acquire that license before distributing the Program.
4. Each Contributor represents that to its knowledge it has sufficient copyright rights in its Contribution, if any, to grant the copyright license set forth in this Agreement.

B.3. Requirements

A Contributor may choose to distribute the Program in object code form under its own license agreement, provided that:

1. it complies with the terms and conditions of this Agreement; and
2. its license agreement:
 - a. effectively disclaims on behalf of all Contributors all warranties and conditions, express and implied, including warranties or conditions of title and non-infringement, and implied warranties or conditions of merchantability and fitness for a particular purpose;
 - b. effectively excludes on behalf of all Contributors all liability for damages, including direct, indirect, special, incidental and consequential damages, such as lost profits;
 - c. states that any provisions which differ from this Agreement are offered by that Contributor alone and not by any other party; and
 - d. states that source code for the Program is available from such Contributor, and informs licensees how to obtain it in a reasonable manner on or through a medium customarily used for software exchange.

When the Program is made available in source code form:

1. it must be made available under this Agreement; and
2. a copy of this Agreement must be included with each copy of the Program.

Contributors may not remove or alter any copyright notices contained within the Program.

Each Contributor must identify itself as the originator of its Contribution, if any, in a manner that reasonably allows subsequent Recipients to identify the originator of the Contribution.

B.4. Commercial Distribution

Commercial distributors of software may accept certain responsibilities with respect to end users, business partners and the like. While this license is intended to facilitate the commercial use of the Program, the Contributor who includes the Program in a commercial product offering should do so in a manner which does not create potential liability for other Contributors. Therefore, if a Contributor includes the Program in a commercial product offering, such Contributor ("Commercial Contributor") hereby agrees to defend and indemnify every other Contributor ("Indemnified Contributor") against any losses, damages and costs (collectively "Losses") arising from claims, lawsuits and other legal actions brought by a third party against the Indemnified Contributor to the extent caused by the acts or omissions of such Commercial Contributor in connection with its distribution of the Program in a commercial product offering. The obligations in this section do not apply to any claims or Losses relating to any actual or alleged intellectual property infringement. In order to qualify, an Indemnified Contributor must: a) promptly notify the Commercial Contributor in writing of such claim, and b) allow the Commercial Contributor to control, and cooperate with the Commercial Contributor in, the defense and any related settlement negotiations. The Indemnified Contributor may participate in any such claim at its own expense.

For example, a Contributor might include the Program in a commercial product offering, Product X. That Contributor is then a Commercial Contributor. If that Commercial Contributor then makes performance claims, or offers warranties related to Product X, those performance claims and warranties are such Commercial Contributor's responsibility alone. Under this section, the Commercial Contributor would have to defend claims against the other Contributors related to those performance claims and warranties, and if a court requires any other Contributor to pay any damages as a result, the Commercial Contributor must pay those damages.

B.5. No Warranty

EXCEPT AS EXPRESSLY SET FORTH IN THIS AGREEMENT, THE PROGRAM IS PROVIDED ON AN "AS IS" BASIS, WITHOUT WARRANTIES OR CONDITIONS OF ANY KIND, EITHER EXPRESS OR IMPLIED INCLUDING, WITHOUT LIMITATION, ANY WARRANTIES OR CONDITIONS OF TITLE, NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Each Recipient is solely responsible for determining the appropriateness of using and distributing the Program and assumes all risks associated with its exercise of rights under this Agreement, including but not limited to the risks and costs of program errors, compliance with applicable laws, damage to or loss of data, programs or equipment, and unavailability or interruption of operations.

B.6. Disclaimer of Liability

EXCEPT AS EXPRESSLY SET FORTH IN THIS AGREEMENT, NEITHER RECIPIENT NOR ANY CONTRIBUTORS SHALL HAVE ANY LIABILITY FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING WITHOUT LIMITATION LOST PROFITS), HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OR DISTRIBUTION OF THE

PROGRAM OR THE EXERCISE OF ANY RIGHTS GRANTED HEREUNDER, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGES.

B.7. General

If any provision of this Agreement is invalid or unenforceable under applicable law, it shall not affect the validity or enforceability of the remainder of the terms of this Agreement, and without further action by the parties hereto, such provision shall be reformed to the minimum extent necessary to make such provision valid and enforceable.

If Recipient institutes patent litigation against a Contributor with respect to a patent applicable to software (including a cross-claim or counterclaim in a lawsuit), then any patent licenses granted by that Contributor to such Recipient under this Agreement shall terminate as of the date such litigation is filed. In addition, if Recipient institutes patent litigation against any entity (including a cross-claim or counterclaim in a lawsuit) alleging that the Program itself (excluding combinations of the Program with other software or hardware) infringes such Recipient's patent(s), then such Recipient's rights granted under Section 2(b) shall terminate as of the date such litigation is filed.

All Recipient's rights under this Agreement shall terminate if it fails to comply with any of the material terms or conditions of this Agreement and does not cure such failure in a reasonable period of time after becoming aware of such noncompliance. If all Recipient's rights under this Agreement terminate, Recipient agrees to cease use and distribution of the Program as soon as reasonably practicable. However, Recipient's obligations under this Agreement and any licenses granted by Recipient relating to the Program shall continue and survive.

Everyone is permitted to copy and distribute copies of this Agreement, but in order to avoid inconsistency the Agreement is copyrighted and may only be modified in the following manner. The Agreement Steward reserves the right to publish new versions (including revisions) of this Agreement from time to time. No one other than the Agreement Steward has the right to modify this Agreement. IBM is the initial Agreement Steward. IBM may assign the responsibility to serve as the Agreement Steward to a suitable separate entity. Each new version of the Agreement will be given a distinguishing version number. The Program (including Contributions) may always be distributed subject to the version of the Agreement under which it was received. In addition, after a new version of the Agreement is published, Contributor may elect to distribute the Program (including its Contributions) under the new version. Except as expressly stated in Sections 2(a) and 2(b) above, Recipient receives no rights or licenses to the intellectual property of any Contributor under this Agreement, whether expressly, by implication, estoppel or otherwise. All rights in the Program not expressly granted under this Agreement are reserved.

This Agreement is governed by the laws of the State of New York and the intellectual property laws of the United States of America. No party to this Agreement will bring a legal action under this Agreement more than one year after the cause of action arose. Each party waives its rights to a jury trial in any resulting litigation.

Index

A

accepting a socket connection, [12](#)

B

binding to a port, [14](#)

C

closing a socket, [15](#), [39](#)
Common Public License, [43](#)
connect to a host, [16](#)
connection, accepting a socket, [12](#)
connection, listen on a socket for a, [25](#)
CPL, [43](#)

D

data on socket, receive, [27](#), [28](#)
data on socket, send, [31](#), [32](#)
definition of a socket, [1](#)
description, RxSock, [1](#)
dropping functions, [12](#)

E

error messages, writing, [26](#)
error, get last socket, [38](#)

F

function
 SockAccept, [12](#)
 SockBind, [14](#)
 SockClose, [15](#)
 SockConnect, [16](#)
 SockDropFuncs, [12](#)

SockGetHostByAddr, [18](#)
SockGetHostById, [19](#)
SockGetHostByName, [18](#)
SockGetPeerName, [19](#)
SockGetSockName, [20](#)
SockGetSockOpt, [21](#)
SockInit, [24](#)
SockIoctl, [24](#)
SockListen, [25](#)
SockLoadFuncs, [12](#)
SockPSock, [26](#)
SockRecv, [27](#)
SockRecvFrom, [28](#)
SockSelect, [29](#)
SockSend, [31](#)
SockSendTo, [32](#)
SockSetSockOpt, [34](#)
SockShutDown, [37](#)
SockSocket, [38](#)
SockSock_Errno, [38](#)
SockSoClose, [39](#)
SockVersion, [12](#)

function parameters, [5](#)
function return values, [5](#)
functions, dropping, [12](#)
functions, list of, [11](#)
functions, loading, [12](#)
functions, version of, [12](#)

G

get a new socket, [38](#)
get last socket error, [38](#)

H

host information, lookup, [18](#), [18](#)
host name, lookup remote connected, [19](#)
host, connect to a, [16](#)

I

initialize a socket, [24](#)
installation, RxSock, [3](#)

L

- License, Common Public, [43](#)
- License, Open Object Rexx, [43](#)
- list of functions, [11](#)
- listen on a socket for a connection, [25](#)
- loading functions, [12](#)
- local host ip address, lookup, [19](#)
- local socket name, lookup, [20](#)
- lookup host information, [18](#), [18](#)
- lookup local host ip address, [19](#)
- lookup local socket name, [20](#)
- lookup remote connected host name, [19](#)

M

- monitor a socket, [29](#)

N

- new socket, get a, [38](#)
- Notices, [41](#)

O

- ooRexx License, [43](#)
- Open Object Rexx License, [43](#)
- option of a socket, set an, [34](#)

P

- parameters, function, [5](#)
- port, binding to a, [14](#)

R

- receive data on socket, [27](#), [28](#)
- registering functions, [12](#)
- retrieve socket options, [21](#)
- return values, function, [5](#)
- RxSock description, [1](#)
- RxSock installation, [3](#)

S

- send data on socket, [31](#), [32](#)
- set an option of a socket, [34](#)
- shutdown a socket, [37](#)
- SocketAccept, [12](#)
- SocketBind, [14](#)
- SocketClose, [15](#)
- SocketConnect, [16](#)
- SocketDropFuncs, [12](#)
- socket error, get last, [38](#)
- socket options, retrieve, [21](#)
- socket special operations, [24](#)
- socket, definition of a, [1](#)
- socket, get a new, [38](#)
- socket, initialize a, [24](#)
- socket, monitor a, [29](#)
- socket, shutdown a, [37](#)
- socket, status of a, [29](#)
- SocketGetHostAddr, [18](#)
- SocketGetHostId, [19](#)
- SocketGetHostName, [18](#)
- SocketGetPeerName, [19](#)
- SocketGetSockName, [20](#)
- SocketGetSockOpt, [21](#)
- SocketInit, [24](#)
- SocketIoctl, [24](#)
- SocketListen, [25](#)
- SocketLoadFuncs, [12](#)
- SocketPSock, [26](#)
- SocketRecv, [27](#)
- SocketRecvFrom, [28](#)
- SocketSelect, [29](#)
- SocketSend, [31](#)
- SocketSendTo, [32](#)
- SocketSetSockOpt, [34](#)
- SocketShutDown, [37](#)
- SocketSocket, [38](#)
- SocketSock_Erno, [38](#)
- SocketSoClose, [39](#)
- SocketVersion, [12](#)
- special operations, socket, [24](#)
- special variables, [9](#)
- status of a socket, [29](#)
- stem variables, usage of, [6](#)

T

TCP/IP, [1](#)

U

usage of stem variables, [6](#)

V

variables, special, [9](#)

version of functions, [12](#)

W

writing error messages, [26](#)

